



How to release the Unsigned Driver in Windows 8 / 8.1 and 10.


Windows 8 / 8.1 and 10 don't let you install unsigned drivers. The following message appears during installation unsigned drivers.




In order to install the MB2 driver, follow the steps below to execute *Disable Driver Signature Enforcement* mode.


1. Go to "Control Panel Home" → "System and Security" → "Security and Maintenance" or "Action Center"





2. Click "Change Windows SmartScreen settings" and choose the bottom "Don't do anything (turn off Windows SmartScreen)" and click "OK" button






3. Select "Restart" from the power options menu and hold down the "SHIFT" key while you click Restart. Otherwise go to "Settings" → "Update & security" → "Recovery" → "Restart now" in the Advanced startup.

Once your computer has rebooted you will be able to choose the Troubleshoot option.

Go to "Troubleshoot" → "Advanced options" → "Startup Settings" → "Restart"





← Troubleshoot

 **Refresh your PC**
If your PC isn't running well, you can refresh it without losing your files

 **Reset your PC**
If you want to remove all of your files, you can reset your PC completely

 **Advanced options**

← Advanced options

 **System Restore**
Use a restore point recorded on your PC to restore Windows

 **Command Prompt**
Use the Command Prompt for advanced troubleshooting

 **System Image Recovery**
Recover Windows using a specific system image file

 **Startup Settings**
Change Windows startup behavior

 **Automatic Repair**
Fix problems that keep Windows from loading


← Startup Settings

Restart to change Windows options such as:

- Enable low-resolution video mode
- Enable debugging mode
- Enable boot logging
- Enable Safe Mode
- Disable driver signature enforcement
- Disable early-launch anti-malware protection
- Disable automatic restart on system failure



4. During restarting, the following “Startup Settings” menu comes up and select “7) Disable driver signature enforcement” by pushing keyboard 7.



The MB2 USB driver now can install, refer to “Quick Setup Guide”.

After finish the installation of MB2 USB driver, we recommend you back to the default setting. Back to “Control Panel” → “System and Security” → “System and Maintenance” or “Action Center” → “Change Windows SmartScreen settings” and choose “Get administrator approval……” and click “OK” button.

